

Konfigurasi Samba di OpenWrt di HG553-ku

Letaknya di /etc/config/samba/

```
config samba
    option name 'OpenWrt'
    option workgroup 'WORKGROUP'
    option description 'OpenWrt'
    option homes '1'

config sambashare
    option name 'mudah'
    option guest_ok 'yes'
    option path '/home/mudah'
    option read_only 'yes'

config sambashare
    option name 'sarip'
    option guest_ok 'yes'
    option path '/home/sarip'
    option read_only 'yes'
```

versi lain di /etc/samba/smb.conf

```
[global]
    netbios name = OpenWrt
    display charset = UTF-8
    interfaces = 127.0.0.1/8 lo 2.2.2.2/24 br-lan
    server string = OpenWrt
    unix charset = UTF-8
    workgroup = WORKGROUP
    browseable = yes
    deadtime = 30
    domain master = yes
    encrypt passwords = true
    enable core files = no
    guest account = nobody
    guest ok = yes
    invalid users = root
    local master = yes
    load printers = no
    map to guest = Bad User
    max protocol = SMB2
    min receivefile size = 16384
    null passwords = yes
    obey pam restrictions = yes
    os level = 20
    passdb backend = smbpasswd
    preferred master = yes
    printable = no
```

```
security = user
smb encrypt = disabled
smb passwd file = /etc/samba/smbpasswd
socket options = TCP_NODELAY IPTOS_LOWDELAY
syslog = 2
use sendfile = yes
writeable = yes
```

```
[homes]
comment = Home Directories
browsable = no
read only = no
create mode = 0750
```

```
[mudah]
path = /home/mudah
read only = yes
guest ok = yes
```

```
[sarip]
path = /home/sarip
read only = yes
guest ok = yes
```

NOTE : untuk efektifitas transfer, pada bagian **use sendfile = yes** diganti **no**.

From:
<https://wiki.samsul.web.id/> - **Samsul Maarif**

Permanent link:
<https://wiki.samsul.web.id/linux/OpenWrt/HG553/samba?rev=1461335024>

Last update: **2020/12/14 20:13**

